

Freight Yard Manager - Installation Notes

**** FYM Requirements

- 1.0 FYM runs on all current versions of Microsoft's Windows, - Windows 2000, Windows XP, Windows Vista, Windows 7 including both 32 and 64 bit variations.
- 2.0 FYM requires DirectX 9.0c. Windows 7 users will need to download and install DirectX 9.0c from Microsoft.
- 3.0 FYM requires Net Framework V2.0 or later.
- 4.0 Please ensure that your Windows version and NET Framework are up to date with all of Microsoft's upgrades.
- 5.0 A Graphics card with at least 32MB memory.
- 6.0 If you wish to download the full network of maps (over 1000) you will need at least 2.5 GB disk Space. However, the game can be played with much more modest Hard Disk requirements (say 100MB).

To check installed version of DirectX go to Start Menu - Run - then enter dxdiag and hit return. The DirectX version installed will be listed at the bottom of "System Information" on the form which will open.

To check NET Framework version installed
Open Control Panel - Double click on Add or Remove Programs
Scroll down list and confirm "Microsoft NET Framework 2 Service Pack 2" or later is installed.

If either of these are missing you can download them free from Microsoft. Google "MSDN Downloads".

**** FYM Install

The following applies to ALL versions of Windows i.e. ALL Installations.

- 1.0 Download the DirectX add-ons in file FYM-DirectX-Redist-XP-2000-Vista-7.zip to any folder and unzip into that folder.
- 2.0 Run dxsetup.exe
- 3.0 Download FYMDist.zip to any folder and unzip into that folder.
- 4.0 Run fymsetup.exe
- 5.0 You will be prompted for a <ROOT> folder - this is where the FYM files and folders will be created.

N.B. when choosing the <ROOT> folder you MUST NOT choose the folder from which you are running fymsetup.exe. Also if you are running Vista or Windows 7 it is recommended that you do not choose a folder in the "Program Files" structure.

Recommended choices for <ROOT> are:

C:\FYM\
C:\My Documents\FYM\
D:\FYM

- 6.0 To complete the installation ensure you have a live internet connection before opening FYManager.exe from the <ROOT> folder.